

# UNIXCOMM

---

UNIXComm starts up a UNIX process on a Sun Workstation. UNIXComm, with two functions, provides the user with a stream interface to the SunOS Bourne shell.

## Installation

---

Load UNIXCOMM.LCOM from the library.

## User Interface

---

Two functions allow you to open and close SunOS subprocess streams.

(IL:CREATE-PROCESS-STREAM *STRING*) [Function]

Interfaces to the SunOS system function (see Chapter 3 of the *SunOS Reference Manual*). This causes a subprocess running the Bourne shell to be spawned; *STRING* is passed as a command to it. A bidirectional stream is returned with input reading data which the process writes to its standard output (`stdout`) and standard error (`stderr`). Output writes data which the process can read from its standard input (`stdin`). EOFP does not return a meaningful value for those streams; instead, you must change the default EOF mechanism for the end of stream.

(IL:UNIX-STREAM-CLOSE *STREAM*) [Function]

Returns the numeric status value of the process created by IL:CREATE-PROCESS-STREAM if it has exited; otherwise, kills the process. IL:CLOSE can be used instead of IL:UNIX-STREAM-CLOSE if the process status value is not of interest.

[This page intentionally left blank]