

The Implementation of Device-Independent Graphics Through Imagestreams

filed as {Eris}<LispCore>Internal>Doc>DIGguide.TEdit
written by Herb Jellinek on 2 November 1984
last revision on 26 February 1985

The Interlisp-D system does all image creation through a set of functions and data structures for **device-independent graphics**, known popularly as DIG. DIG is achieved through the use of a special flavor of stream, known as an imagestream.

An imagestream, by convention, is any stream that has its `IMAGEOPS` field (described in detail below) set to a vector of meaningful graphical operations. Using imagestreams, we can write programs that draw and print on an output stream without regard to the underlying device, be it window, disk, Dover, 8044 or Diablo printers. For example, the following have imagestreams backing them: windows, Press streams, Interpress streams, and Iris streams.

Imagestream structure

As indicated above, imagestreams use a field that no other stream does: `IMAGEOPS`. `IMAGEOPS` is an instance of the `IMAGEOPS` datatype, and contains a vector of the stream's graphical methods. The methods contained in the `IMAGEOPS` can make arbitrary use of the stream's `IMAGEDATA` field, which is provided for their use, and may contain any data needed.

`IMAGEOPS`

[Datatype]

The `IMAGEOPS` datatype has the following fields:

`IMAGETYPE` The name of image type. Monochrome display streams have an `IMAGETYPE` of `DISPLAY`; color display streams are identified as `(COLOR DISPLAY)`. The `IMAGETYPE` is informational, and can be set to anything the implementor chooses.

`IMFONTCREATE` The device name to pass to `FONTCREATE` when fonts are created for the stream.

The following fields are all stream methods, and are presented with their arguments, in the manner of a function definition. With the exception of `IMCLOSEFN`, each method that follows has a corresponding function that consists of the method's name with the "IM" prefix removed. All coordinates that refer to points in a display device's space are measured in the device's units. (The `IMSCALE` method provides access to a device's scale.)

(`IMCLOSEFN` *STREAM*)

What to do before stream is `CLOSEF`ed, e.g. flush buffers, write header or trailer information, etc.

(`IMDRAWLINE` *STREAM X1 Y1 X2 Y2 WIDTH OPERATION COLOR*)

Draws a line of width *WIDTH* from (*X1*, *Y1*) to (*X2*, *Y2*). (Dashing is currently handled at a higher level, and thus is not an argument).

(`IMDRAWCURVE` *STREAM KNOTS CLOSED BRUSH DASHING*)

Draws a curve through *KNOTS*.

(`IMDRAWCIRCLE` *STREAM CENTERX CENTERY RADIUS BRUSH DASHING*)

Draws a circle of radius *RADIUS* around (*CENTERX*, *CENTERY*).

(`IMDRAWELLIPSE` *STREAM CENTERX CENTERY SEMIMINORRADIUS SEMIMAJORRADIUS ORIENTATION BRUSH DASHING*)

Draws an ellipse around (*CENTERX*, *CENTERY*).

(*IMFILLCIRCLE STREAM CENTERX CENTERY RADIUS TEXTURE*)

Draws a circle filled with texture *TEXTURE* around (*CENTERX*, *CENTERY*).

(*IMBLTSHADE TEXTURE STREAM DESTINATIONLEFT DESTINATIONBOTTOM WIDTH HEIGHT OPERATION CLIPPINGREGION*)

The texture-source case of *BITBLT*. *DESTINATIONLEFT*, *DESTINATIONBOTTOM*, *WIDTH*, *HEIGHT*, and *CLIPPINGREGION* are measured in *STREAM*'s units. This method is invoked by the functions *BITBLT* and *BLTSHADE*.

(*IMBITBLT SOURCEBITMAP SOURCELEFT SOURCEBOTTOM STREAM DESTINATIONLEFT DESTINATIONBOTTOM WIDTH HEIGHT SOURCETYPE OPERATION TEXTURE CLIPPINGREGION CLIPPEDSOURCELEFT CLIPPEDSOURCEBOTTOM*)

The bitmap-source cases of *BITBLT*. *SOURCELEFT*, *SOURCEBOTTOM*, *CLIPPEDSOURCELEFT*, *CLIPPEDSOURCEBOTTOM*, *WIDTH*, and *HEIGHT* are measured in pixels; *DESTINATIONLEFT*, *DESTINATIONBOTTOM*, and *CLIPPINGREGION* are in the units of the destination stream.

(*IMSCALEDBITBLT SOURCEBITMAP SOURCELEFT SOURCEBOTTOM STREAM DESTINATIONLEFT DESTINATIONBOTTOM WIDTH HEIGHT SOURCETYPE OPERATION TEXTURE CLIPPINGREGION CLIPPEDSOURCELEFT CLIPPEDSOURCEBOTTOM SCALE*)

A scaled version of *IMBITBLT*. Each pixel in *SOURCEBITMAP* is replicated *SCALE* times in the X and Y directions; currently, *SCALE* must be an integer.

(*IMMOVETO STREAM X Y*)

Move to (*X*,*Y*). This method is invoked by the functions *MOVETO* and *RELMOVETO*. If it is not supplied, a default method composed of calls to the *IMXPOSITION* and *IMYPOSITION* methods is used.

(*IMTERPRI STREAM*)

(As yet unused.) Issue a newline. When implemented, this method will be invoked by the function *TERPRI*. It defaults to (*\OUTCHAR STREAM (CHARCODE EOL)*) .

(*IMSTRINGWIDTH STREAM STR RDTBL*)

Returns the width of string *STR* in *STREAM*'s units, using *STREAM*'s current font. If this method is not supplied, it defaults to calling *\STRINGWIDTH.GENERIC* .

(*IMCHARWIDTH STREAM CHARCODE*)

Returns the width of character *CHARCODE* in *STREAM*'s units. If this method is not supplied, it defaults to calling *\STRINGWIDTH.GENERIC* .

The following methods all have corresponding *DSPxx* functions (e.g. *IMYPOSITION* corresponds to *DSPYPOSITION*) that invoke them. They also have the property that they return their previous value; when called with *NIL* they return the old value without changing it.

(*IMXPOSITION STREAM XPOSITION*)

Sets new x-position on *STREAM*.

(*IMYPOSITION STREAM YPOSITION*)

Sets new y-position on *STREAM*.

(*IMFONT STREAM FONT*)

Sets *STREAM*'s font to be *FONT*.

(IMLEFTMARGIN *STREAM LEFTMARGIN*)

Sets *STREAM*'s left margin to be *LEFTMARGIN*. The left margin is defined as the x position set after newline.

(IMRIGHTMARGIN *STREAM RIGHTMARGIN*)

Sets *STREAM*'s right margin to be *RIGHTMARGIN*. The right margin is defined as the maximum x position at which characters will be printed; printing beyond it causes a newline.

(IMLINEFEED *STREAM DELTA*)

Sets *STREAM*'s linefeed distance (distance to move vertically after a newline) to be *DELTA*.

(IMNEWPAGE *STREAM*)

Causes a new page to be started; the position is set to (*DSPLEFTMARGIN*, *DSPTOPMARGIN*). If not supplied, defaults to (`\OUTCHAR STREAM (CHARCODE ↑L)`).

(IMSCALE *STREAM SCALE*)

Returns the number of device points per screen point (a screen point being $\sim 1/72$ inch). In a later release of Interlisp-D the conversion factor will be specifiable. (I.e. right now *SCALE* is ignored.)

(IMTOPMARGIN *STREAM YPOSITION*)

Sets *STREAM*'s top margin (the y-position of the tops of characters that is set after newpage) to be *YPOSITION*.

(IMBOTTOMMARGIN *STREAM YPOSITION*)

Sets *STREAM*'s bottom margin (the y-position beyond which any printing causes a newpage) to be *YPOSITION*.

(IMSPACEFACTOR *STREAM FACTOR*)

Sets the amount by which to multiply the natural width of all following space characters on *STREAM*: used for justification of text. The default value is 1. For example, if the natural width of a space in *STREAM*'s current font is 12 units, and the spacefactor is set to 2, spaces will appear 24 units wide. The values returned by `STRINGWIDTH` and `CHARWIDTH` will also be affected.

(IMOPERATION *STREAM OPERATION*)

Sets the default `BITBLT OPERATION` argument. See the `DSPOPERATION` and `BITBLT` documentation for more information.

(IMBACKCOLOR *STREAM COLOR*)

Sets the background color of *STREAM*.

(IMCOLOR *STREAM COLOR*)

Sets the default color of *STREAM*.

In addition to the `IMAGEOPS`-borne methods described above, there are two other important methods, which are contained in the stream itself.

`STRMBOUTFN`

[Stream Method]

Function called by BOUT. You can install a STRMBOUTFN in a stream *STREAM* using the form (**replace** (STREAM STRMBOUTFN) **of** STREAM **with** (FUNCTION MYBOUTFN)).

OUTCHARFN

[Stream Method]

This is the function that is called to output a single byte. This is like STRMBOUTFN, except for being one level higher: it is intended for text output. Hence, this function should convert (CHARCODE EOL) into the stream's actual end of line sequence, and should adjust the stream's CHARPOSITION appropriately before invoking the stream's STRMBOUTFN (by calling BOUT) to actually put the character. Defaults to \FILEOUTCHARFN, which is definitely NOT what you want. OUTCHARFNs are installed using a form like (**replace** (STREAM OUTCHARFN) **of** STREAM **with** (FUNCTION MYOUTCHARFN)).

IMAGEDATA

[Record field]

Used to hold data pertaining to this type of imagestream; the content is completely up to the implementor. For Interpress devices, this is an instance of the datatype INTERPRESSDATA; for Press, PRESSDATA; for the display, \DISPLAYDATA.

Creating imagestreams

(OPENIMAGESTREAM *FILE* *IMAGETYPE* *OPTIONS*)

[function]

Opens and returns an output stream of type *IMAGETYPE* (PRESS, INTERPRESS, DISPLAY or other types) on a destination specified by *FILE*. *FILE* can name a file either on a normal storage device or on a printer device. In the latter case, the file is sent to the printer when the stream is closed. Because of the way that defaulted arguments are interpreted, OPENIMAGESTREAM provides a convenient and standard interface for interpreting user output-destination specifications.

If *IMAGETYPE* is NIL, the image type is inferred from the extension field of *FILE* and the EXTENSIONS properties in the list PRINTFILETYPES. Thus, a PRESS extension denotes a Press-format stream, while IP, IPR, and INTERPRESS indicate Interpress format. If *FILE* has no extension but is a file on the printer device {LPT}, then *IMAGETYPE* will be the type that the indicated printer can print. If *FILE* has no extension but is not on the printer device, then *IMAGETYPE* will default to the type accepted by the first printer on DEFAULTPRINTINGHOST.

FILE = NIL is equivalent to *FILE* = {LPT}. Names for printer files are of the form {LPT}PRINTERNAME.TYPE, where PRINTERNAME, TYPE, or both may be omitted. PRINTERNAME is the name of the particular printer to which the file will be transmitted on closing; it defaults to the first printer on DEFAULTPRINTINGHOST that can print *IMAGETYPE* files. As just described, the TYPE extension supplies the *IMAGETYPE* when it is defaulted. OPENIMAGESTREAM will generate an error if the specified printer does not accept the kind of file specified by *IMAGETYPE*.

Examples assuming IP: is an Interpress printer, P is a Press printer, and DEFAULTPRINTINGHOST is (IP: P):

(OPENIMAGESTREAM) returns an Interpress image stream on printer IP:

(OPENIMAGESTREAM NIL 'PRESS) returns a Press stream on P

(OPENIMAGESTREAM '{LPT}.INTERPRESS) returns an Interpress stream on IP:

(OPENIMAGESTREAM '{CORE}FOO.PRESS) returns a Press stream on the file {CORE}FOO.PRESS

For completeness and consistency, if *IMAGETYPE* is inferred to be DISPLAY, then the user is prompted for a window to open. The file name in this case will be used as the title of the window.

OPTIONS is a list in property list format that may be used to specify certain attributes of the image stream; not all attributes are meaningful or interpreted by all types of streams. Among the properties are:

REGION value is the region on the page (in stream scale units, 0,0 being the lower-left corner of the page) that text will fill up. It establishes the initial values for *DSPLEFTMARGIN*, *DSPRIGHTMARGIN*, *DSPBOTTOMMARGIN* and *DSPTOPMARGIN*.

FONTS value is a list of fonts that are expected to be used in the stream. Some streams (e.g. Interpress) are more efficient if the expected fonts are called out in advance, but this is not necessary. The first font in this list will be the initial font of the stream, otherwise the *DEFAULTFONT* for that image type will be used.

HEADING the heading to be placed automatically on each page, *NIL* means no heading.

IMAGESTREAMTYPES

[a-list]

Describes how to create a stream for a given image type. Contains *OPENSTREAM*, *FONTCREATE*, *FONTSAVAILABLE* methods. The main a-list is indexed by the image-stream type name (e.g., *DISPLAY*, *PRESS*, or *INTERPRESS*) to get another a-list that associates device-dependent functions with generic operation names.

Format of a single a-list entry:

```
(imagetype
 (OPENSTREAM function-to-open-the-stream)
 (FONTCREATE function-to-create-a-fontdescriptor)
 (FONTSAVAILABLE function-to-return-available-fonts))
```

For example, for Interpress, the a-list entry is:

```
(INTERPRESS
 (OPENSTREAM OPENIPSTREAM)
 (FONTCREATE \CREATEINTERPRESSFONT)
 (FONTSAVAILABLE \SEARCHINTERPRESSFONTS))
```

The *OPENSTREAM* function is called with arguments:

```
(openstreamfn FILE OPTIONS)
```

FILE is the file name as it was passed to *OPENIMAGESTREAM*, and *OPTIONS* is the *OPTIONS* property list passed to *OPENIMAGESTREAM*. The result must be a stream of the appropriate imagetype.

The *FONTCREATE* function is called with arguments:

```
(fontcreatefn FAMILY SIZE FACE ROTATION DEVICE)
```

FAMILY is the family name for the font, e.g. *MODERN*. *SIZE* is the body size of the font, in printer's points. *FACE* is a 3-element list describing the weight, slope, and expansion of the face desired, e.g. (*MEDIUM ITALIC EXPANDED*). *ROTATION* is how much the font is to be rotated from the normal orientation, in minutes of arc. For example, to print a landscape page, fonts would have rotation 5400 (=90 degrees). The function's result must be a *FONTDESCRIPTOR* with the fields filled in appropriately.

The *FONTSAVAILABLE* function is called with arguments:

```
(fontsaveavailablefn FAMILY SIZE FACE ROTATION DEVICE)
```

This function returns a list of all fonts agreeing with the *FAMILY*, *SIZE*, *FACE*, and *ROTATION* arguments; any of them may be wildcarded (i.e. equal to '* , which means "any"). Each

element of the list should be a 5-tuple of the form (FAMILY SIZE FACE ROTATION DEVICE).

Where the function looks is an implementation decision: the `fontsaveavailablefn` for the display device looks at `DISPLAYFONTDIRECTORIES`, the Interpress code looks on `INTERPRESSFONTDIRECTORIES`, and implementors of new devices should feel free to introduce new search path variables.

Imagestream predicates

(IMAGESTREAMP *X* *IMAGETYPE*) [function]

Returns *X* (possibly coerced to a stream) if it is an output image stream of type *IMAGETYPE* (or of any type if *IMAGETYPE* = NIL), otherwise NIL.

(IMAGESTREAMTYPE *STREAM*) [function]

Returns the image type of *STREAM*.

(IMAGESTREAMTYPEP *STREAM* *TYPE*) [function]

Returns T if *STREAM* is an imagestream of type *TYPE*.

Creating your own flavor of imagestream

In accomplishing a task as complex as building a new flavor of imagestream, no document can contain all of the answers, tricks, or shortcuts. There is no substitute for studying a working implementation in doing your own. Therefore, we recommend you look at the `FX80STREAM` package as an example of how to create a new imaging device. `FX80STREAM` is a DIG interface for the Epson FX-80 printer - a device simple enough to drive that its details will not obscure the fundamentals of how its imagestream works.